


# **Presentation Purpose**

- Discuss Triad investigation approach.
- Explain NAPL characterization tools used at EGDY.
- Discuss CSM of EGDY DNAPL.



# **EGDY History**

- Received Logistics Center wastes from 1946 – 1970's.
- Cleaning and degreasing solvents and POLs.
- Disposed in trenches in drums, free liquid or burned.



## **EGDY Characterization Methods**

- Dynamic investigation approach.
- Systematic planning.
- Real time data collection.
- Qualified field personnel.

# **Investigation Chronology**

- Two phases due to funding constraints.
- Phase I: 1998 1999.
- EE/CA.
- Drum Removal Action.
- Phase II: 2001 2002.

## Phase I DQOs


- Evaluate if significant NAPL present beneath EGDY to provide continuing source of TCE to groundwater.
- Estimate extent of LNAPL and DNAPL if present.
- Refine hydrogeologic understanding.





#### Phase I Toolbox


- Aerial photography.
- EM-61.
- Soil gas sampling.
- Exploratory trenches.
- Drive point groundwater sampling.
- On site GC analysis.















# Direct Push Drive Point Groundwater Sampling






#### EE/CA

- Purpose: to evaluate remedial alternatives to accelerate cleanup and reduce overall costs.
- Preferred alternative:
  - Optimize P&T system.
  - Remove source area drums.
  - Thermal treatment of NAPL contaminated source soils and groundwater.





## Phase II DQOs

- Obtain data for NAPL thermal treatment design.
- Obtain data for P&T optimization.
- Obtain data for reactive barrier wall options.
- Provide analytical results to segregate and classify IDW.
- Field generated data turnaround time supports realtime decision making needs.




### Phase II Toolbox


- SCAPS LIF.
- Geoprobe MIP.
- Resistivity and GPR.
- Sonic Coring.
  - UV fluorescence.
  - Sheen tests.
  - Hydrophobic dye tests.
  - PID.
- Soil physical analyses.
- Multi-port wells.

















# **TCE Mass Estimate**

	TCE	
Description	Mass (lbs)	Volume (gal)
Drum Removal	50,000	4,000
Remaining NAPL	100,000	10,000
Dissolved Plume	10,000	1,000

# **TPH Mass Estimate**

	ТРН	
Description	Mass (lbs)	Volume (gal)
Drum Removal	100,000	20,000
Remaining NAPL	600,000	80,000
Dissolved Plume		

#### Conclusions

- Triad investigation method:
  - Insured adequate data for thermal design.
  - Reduced investigation time.
- Contract for thermal remediation awarded September 2002.
- Thermal treatment to begin late 2003.